

Network license server installation

1. Extract the contents of the license server installation package "**3DE141LicenseServer_x64.zip**" to a folder (e.g. **C:\reprise**) in the license server machine.
2. Run the commands "rlmhostid ether" and "hostname" to get machine information for creating the license.
3. Send the machine information to DeskArtes to get a license.
4. Copy the received license file (e.g. **3DataExpert141.lic**) to the license server folder.
5. Install rlm to be run as a Windows service with command

```
rlm.exe -install_service -service_name rlm-deskartes -dlog  
c:\reprise\reprise\log.txt -c c:\reprise\3DataExpert141.lic
```

6. Start rlm service (e.g. **rlm-deskartes**) using the Windows Services control panel.
7. Test with a web browser (**http://localhost:5054**) that license server is running.

For more detailed instructions for installing the license server, see the document "**Network license setup: Server installation**".

Network license client settings

1. Select "**Help->Licenses**" menu command in 3Data Expert.
2. Select "**License mode: Network**".
3. Click the "**Setup license server connection**" button.
4. Fill in the license server **address** and **port number** and click OK.
5. Restart 3Data Expert.

For more detailed instructions for configuring the 3Data Expert to use the network license, see the document "**Network license setup: Client settings**".